

# Workflow

## Step 0: Getting set up

**Download the Data:** Get what you need from the ALMA archive

**Program Overview:** Get familiar with the program setup, the pipeline products, and what happened at the AOS

**Restoring the Pipeline Calibration:** Get the calibrated data

**Inspecting the Weblog:** Understand how the pipeline calibration went

**Useful Dictionaries:** Create useful dictionaries for the reduction and imaging process

## Step 1: Prepare the continuum

**Manual Flagging:** Apply any manual flags

**Pseudo-continuum Measurement Sets:** Split out the continuum spectral windows, with the line spectral windows averaged down and spectral lines flagged

**Initial Continuum Images:** Create initial continuum images for each execution block and each spectral window

**Initial Self-Calibration:** Perform one initial round of self-calibration, on each execution block

## Step 2: Phase alignment (detour to modular CASA)

**Align Long-Baseline Execution Blocks:** Align LB execution blocks to a chosen LB reference execution

**Align Short-Baseline Execution Blocks:** Align SB execution blocks to the concatenation of aligned LB executions

## Step 3: Self-calibration of the continuum

**Self-Calibration of Short-Baseline Execution Blocks:** Self-calibrate the aligned SB executions

**Self-Calibration of SB+LB Data:** Self-calibrate the aligned SB and LB executions

**Create Final Continuum Measurement Set:** Final continuum measurement set (1 in total) achieved! 🥳

## Step 4: Prepare the lines

**Manual Flagging:** Apply any manual flags

**Splitting Out Line Spectral Windows:** Split out the line spectral windows, with the continuum spectral windows averaged down

**Apply Phase Shifts:** Apply the same phase alignments as determined for the continuum

**Apply Self-Calibration Solutions:** Apply the same self-calibration solutions as determined for the continuum

**Continuum Subtraction:** Perform continuum subtraction in uv-space

**Create Final Line Measurement Sets:** Split spectral windows out of each execution block, then combine across execution blocks. Final measurement sets (8 in total) achieved! 🥳

## Proceed to Imaging